



## CONFIGURATION GUIDE

# Using MailMarshal Cloud with Google G Suite

## Table of Contents

<b>About This Document</b> .....	<b>1</b>
<b>1 MailMarshal Cloud for Anti-Malware with G Suite</b> .....	<b>2</b>
<b>2 Networking and DNS Setup</b> .....	<b>2</b>
<b>3 Provisioning MailMarshal Cloud</b> .....	<b>3</b>
<b>4 Configuring G Suite Email</b> .....	<b>4</b>
4.1 Set up an Outbound Mail Gateway to deliver outgoing messages to MailMarshal Cloud.....	4
4.2 Set up an Inbound Mail Gateway to accept incoming messages from MailMarshal Cloud ...	4
<b>About LevelBlue</b> .....	<b>5</b>
<b>Trademarks</b> .....	<b>5</b>


## About This Document

This document is for the use of email administrators who are using MailMarshal Cloud to accept and filter messages from the Internet, and Google G Suite to host user mailboxes.

The same ideas can be used to configure other cloud-based mailbox hosting solutions. (For Exchange Online, see the separate document with detailed instructions.)

# 1 MailMarshal Cloud for Anti-Malware with G Suite

In this scenario, the organization hosts user mailboxes on a cloud-based service such as Google G Suite Email. The organization uses the MailMarshal Cloud service to provide filtering of spam and malware, and other policy controls for both inbound and outbound messages.



## 2 Networking and DNS Setup

1. Configure MX records for all your local domains to point to the MailMarshal Cloud environment.
2. Add the MailMarshal Cloud server to your SPF record.



**Note:** The settings depend on the regional instance of MailMarshal Cloud configured for your customer account when provisioned. For details of the configuration data required, see MailMarshal Cloud Knowledgebase article Q21095, [MailMarshal Cloud Connection Details](#).

In most cases MX records are updated when you are ready to direct email into the new environment (after all other configuration is complete).

## 3 Provisioning MailMarshal Cloud

Trustwave Provisioning or Managed Security Services must configure MailMarshal Cloud to accept and deliver email for your domains.

1. MailMarshal Cloud will deliver email incoming for your managed domains to the cloud hosting environment. Provide the delivery details to Trustwave.
  - For G Suite email, use the list of servers documented as "G Suite MX record values." At the time this document was last reviewed the values were as in the table below.

Destination Server	Priority
ASPMX.L.GOOGLE.COM	1
ALT1. ASPMX.L.GOOGLE.COM	5
ALT2. ASPMX.L.GOOGLE.COM	5
ALT3. ASPMX.L.GOOGLE.COM	10
ALT4. ASPMX.L.GOOGLE.COM	10

2. MailMarshal Cloud will accept email relaying (messages sent to other domains "from" your managed domains) based on the configured inbound delivery addresses. For G Suite, to ensure that the relaying addresses are up to date, Trustwave will also configure relaying based on the SPF records published by the service.

## 4 Configuring G Suite Email

You will set up two gateways to route email between MailMarshal Cloud and G Suite Email. To complete this step, you must have an Administrator credential for the service.

### 4.1 Set up an Outbound Mail Gateway to deliver outgoing messages to MailMarshal Cloud

1. From the G Suite dashboard, go to Apps > G Suite > Gmail > Advanced settings.
2. In the Organizations section, highlight the top-level org.
3. Scroll down to the Outbound gateway section.

In the Outbound gateway text box, enter the externally resolvable hostname of the MailMarshal Cloud server. For details of the configuration data required, see MailMarshal Cloud Knowledgebase article Q21095, [MailMarshal Cloud Connection Details](#).

4. Save your changes.

### 4.2 Set up an Inbound Mail Gateway to accept incoming messages from MailMarshal Cloud

1. From the G Suite dashboard, go to Apps > G Suite > Gmail > Advanced settings.
2. In the Organizations section, highlight your domain (top-level org).
3. Scroll down to Inbound gateway (you can also enter Inbound gateway in the search field).
4. Hover the cursor to the right of Inbound gateway. To create a new inbound gateway setting, click Configure. To edit an existing setting, click Edit.
5. Under Gateway IPs, enter the IP address range of the MailMarshal Cloud servers. For details of the configuration data required, see MailMarshal Cloud Knowledgebase article Q21095, [MailMarshal Cloud Connection Details](#).
6. Also select **Reject all mail not from gateway IPs** and **Require TLS for connections from the email gateways listed above**.
7. Save your changes.

## About LevelBlue

LevelBlue reduces risk and builds lasting resilience so organizations can innovate and advance their mission with confidence. As the world's most analyst-recognized and largest pure-play managed security services provider, LevelBlue elevates client outcomes that matter: stronger defense, faster response, and sustained business continuity. LevelBlue combines AI-powered security operations, advanced threat intelligence, and elite human expertise to provide the most comprehensive portfolio of strategic advisory, managed security, offensive security, and incident response services.

## Trademarks

G Suite is a trademark of Google, Inc.